




READ THIS FIRST!

BACK UP YOUR ORIGINAL DISKS BEFORE PROCEEDING!

INSTALLING WILL ALTER THE ORIGINAL DISKS SO PLEASE MAKE A BACKUP! Copy all Program disks onto blank disks and save the originals. This is very important! You may need to reinstall or copy from originals again if your running copy becomes unusable or you change your graphics card, memory size, or purchase a Speech Accessory Unit. To make a backup copy insert your DOS boot disk and type DISKCOPY A: B: and follow the prompts.



SYSTEM REQUIREMENTS

Product: The Dinosaur Discovery Kit (MS-DOS)

Memory: 512K or greater

System Disk: DOS Version 2.0 or greater

Graphics: Requires both color monitor & color graphics (CGA, EGA, VGA and Tandy TGA).



RUNNING THE DINOSAUR DISCOVERY KIT

First Time Installation: Insert your disk in the currently active drive, type **INSTALL** then press the Enter or Return key. If you have two 5 1/4" disks insert Disk #1.

Hard Disk: Type **HDINSTALL** *drive letter:* with Disk #1 in the currently active drive, (e.g., **HDINSTALL C:**). This Hard Disk install will automatically create the directory **FIRSTBYT** and it's sub-directory **DINODISC**.

EXAMPLE: \FIRSTBYT\DINODISC

IMPORTANT

Once the installation process is complete, you only need to use the **INSTALL** command again if you change your operating environment with an updated graphics card, speech accessory, or more memory. To re-install, re-copy your original disks onto blank disks and **INSTALL** again from the copies.

Speech: If you have a Tandy SL, TL or Tandy Speech Card, the appropriate driver will be automatically installed. If none of the above are detected, you will be asked if your computer has one of the listed Speech Accessory Units. If you enter **YES**, the Install program will provide you with information regarding attachment procedures for your Speech Accessory Unit. If you do not have a Speech Accessory Unit, answer **NO**. When you run the product, you will be listening to the speech through the computer's

internal speaker. If the volume is insufficient, you can
1) adjust the volume control if one is present, 2) plug head phones or an amplifier into the phone jack if one is supplied, or 3) purchase one of the Speech Accessory Units listed on page 5. A Version 2.0 (standard) or Version 3.0 (best quality) speech module will be installed depending on the speed of your computer and the amount of memory available.

TANDY USERS

Due to the superior sound and speech capabilities of the **Tandy 1000 TL or SL**, if you have an Echo speech board it is recommended that it not be used.

F1 key: Pressing the F1 key at any time during program operation will reveal on-line help and the Helper Control panel.




STARTUP AFTER INSTALLATION

Floppy Disk: Insert Disk #1, type RUN, then press the Enter or Return key. You may, under certain conditions, be prompted to insert Disk #2 (if one is present).

Hard Disk: First Byte automatically creates the directory FIRSTBYT and it's sub-directory DINODISC. You must change the current Hard Disk directory by typing:

- 1) *CD drive letter:\FIRSTBYT\DINODISC*
- 2) Then type RUN and press the Enter or Return key.



KEYBOARD CONTROL

This product is compatible with the Tandy DeskMate conventions. You may press the F1 key at any time to get help with your current activity. Use the arrow keys, Tab, and Shift Tab, to highlight or underline successive items on the screen. Press RETURN, ENTER or the Spacebar Key to select an option. Pressing the ESC (Escape) key at any time will terminate an activity.

PERIPHERALS



Mouse Support: The program supports the following pointer devices: Joystick, or Joystick mouse, Microsoft Bus mouse, Microsoft/TANDY serial mouse, Mouse Systems mouse, Imsi, Genius mouse, or any Microsoft compatible serial mouse. A Joystick must must be activated using the CONFIG command. Note: a Microsoft compatible serial mouse requires a resident mouse driver to be installed prior to use with this product.

Printers: The program supports all IBM, Epson, and TANDY serial or parallel text printers.

Graphics: The program requires the following graphics modes: CGA, EGA, VGA and Tandy TGA.

Monitors: The program requires a color monitor.



ANY QUESTIONS?

First Byte customer support:

OUTSIDE CALIFORNIA
1-800-523-8070

INSIDE CALIFORNIA
1-213-595-7006

Speech accessory information:



HEARSAY INC.
1-718-232-7266

COVOX INC.
1-503-342-1271

STREET ELECTRONICS CORP
1-805-684-4593

First Byte

3100 South Harbor Blvd., Suite 150
Santa Ana, CA 92704
(714) 432-1740

© Tandy & DeskMate are Trademarks of Tandy Corporation.

